

Table of Contents

- [1. Website macros](#)
 - [1.1 Quick start](#)
 - [1.2 Variables](#)
 - [1.3 Macros](#)
 - [1.3.1 heading_counter_reset\(page\)](#)
 - [1.3.2 reference_style\(\) / acronym_style\(\) / glossary_style\(\)](#)
 - [1.4 Status](#)

1. Website macros

`prodockit.zensical_macros` provides a handful of Jinja variables and macros for Zensical's own [macros plugin](#) - the pieces a professional/academic report's website commonly wants that aren't specific to any one project: a site-wide word count, the git-detected repository URL, chapter/appendix numbering that continues across pages, and reference/acronym/glossary list spacing that matches [prodockit.pdf](#)'s own PDF output.

1.1 Quick start

Add it alongside your own project's `macros.py` (which keeps anything genuinely project-specific - a custom macro, institution branding, and so on):

```
[project.markdown_extensions.zensical.extensions.macros]
module_name = "macros"
modules = ["prodockit.zensical_macros"]
```

Zensical's macros plugin loads `module_name` and every entry in `modules`, merging all of their variables/macros into the same Jinja environment - so a project with no macros of its own can drop `module_name` / `macros.py` entirely and just use:

```
[project.markdown_extensions.zensical.extensions.macros]
modules = ["prodockit.zensical_macros"]
```

1.2 Variables

Variable	Description
<code>{{ word_count }}</code>	Prose word count across every nav page except the first (assumed to be the cover page) and any page flagged <code>exclude_from_word_count: true</code> in its own front matter - a comma-formatted string (e.g. <code>"9,971"</code>).
<code>{{ repo_url }}</code>	The fully-qualified <code>https://</code> URL for the current checkout's git <code>origin</code> remote (converted from <code>git@host:path.git</code> SSH syntax, with any embedded CI credentials stripped) - <code>""</code> if there's no git remote configured.
<code>{{ site_name }}</code>	<code>project.site_name</code> from <code>zensical.toml</code> .

1.3 Macros

Macro	Description
<code>{{ heading_counter_reset(page) }}</code>	Place near the top of every page - continues chapter/section numbering (and the matching sidebar numbering) across pages, from this page's position in nav. See below.
<code>{{ reference_style() }}</code>	Place once near the top of a references page - controls <code>.reference</code> paragraph spacing. See below.
<code>{{ acronym_style() }}</code>	Place once near the top of an acronyms page - matches <code>reference_style()</code> 's default spacing.
<code>{{ glossary_style() }}</code>	Place once near the top of a glossary page - matches <code>reference_style()</code> 's default spacing.

1.3.1 `heading_counter_reset(page)`

Emits a `<style>` block that continues heading numbering from wherever the *previous* page left off, using `prodockit.headings.prescan()` - the single source of truth for what number/letter a page actually gets, so this always matches what `\ref{}` resolves to for a heading on this page. Nothing else needs to change when pages are reordered or headings are added/removed.

Set `project.extra.heading_numbering = false` in `zensical.toml` to turn numbering off entirely (content and sidebar) across the whole site. A page flagged `is_appendix: true` in its own front matter gets letter-based numbering instead - "Appendix A", "A.1", "A.1.1" - matching `prodockit.headings`' own `appendix_attr` default.

1.3.2 `reference_style()` / `acronym_style()` / `glossary_style()`

Controls list-entry spacing, driven by the same `project.extra.*` settings `prodockit.pdf` reads for the PDF, so both outputs stay in sync from one configured value:

Setting	Default	What it does
<code>reference_style</code>	<code>"european"</code>	<code>"european"</code> : single line spacing throughout, no indent, entries close together. <code>"global"</code> : single line spacing within each entry, double spacing <i>between</i> entries, with a hanging indent on wrapped lines (the common APA/MLA/Chicago style). Only <code>reference_style()</code> /the References page switches look - acronyms/glossary always use the tight "european" spacing.
<code>reference_spacing_european</code>	<code>"-0.8em"</code>	Gap between entries, "european" style - also used unconditionally for the acronym/glossary lists.
<code>reference_indent_global</code>	<code>"1.27cm"</code>	Hanging indent on wrapped lines, "global" style.
<code>reference_spacing_global</code>	<code>"2em"</code>	Gap between entries, "global" style.

1.4 Status

No formal, versioned public API stability contract yet (see [prodockit-extensions#7](#)).